

Special Functions

BLOCK MOVE COMMANDS:

CONTROL — N: (C) Clears the buffer

CONTROL — N: (S) Saves the text

CONTROL — N: (R) Replaces the text

The BLOCK is defined as the text between the top of the video screen and the current position of the cursor.

PRINTER CONTROL COMMANDS:

CONTROL — N: (P) Changes printer options

CONTROL — N: (L) Lists printer options

ALL CONTROL — N commands are followed with a single non-control character.

SEARCH COMMANDS:

CONTROL — V: Search mode

CONTROL — C: Continue search

SUB-SYSTEM COMMANDS:

CONTROL — K: Goes to DISK FILING SYSTEM

CONTROL — P: Goes to PRINT SUB SYSTEM

CONTROL — O: Exits to BASIC

Helpful Hints

- Put two shift "M"s (return) before typing in text.
- EasyWriter removes extra spaces for efficient memory and disk usage. To add spaces to your text, use the "User Definable Character" (.U%160)
- Your line length must be set to 1 (one) less than your printer's maximum column width, i.e. (.L79) for a 80 column printer. Assume left margin at 0 (.M0).
- Place the end of paragraph command (two shift "M"s) on left side of screen between text lines to separate paragraphs.
- Use (.I0) before centering (.C). Indentation effects centering.

User Definable Characters

Maybe the single most powerful feature of EasyWriter is the ability to substitute any keyboard character with another ASCII value. For example (.U%160) will substitute a space everytime the "%" is encountered. (.U\$223) will substitute an underline in place of the "\$" character.

Apple ASCII Character Set

DEC #	CHARACTER	DEC #	CHARACTER	DEC #	CHARACTER
128	NULL	171	+	214	V
129	CTRL A	172	=	215	W
130	CTRL B	173	-	216	X
131	CTRL C	174	.	217	Y
132	CTRL D	175	/	218	Z
133	CTRL E	176	0	219	[
134	CTRL F	177	1	220	\
135	BELL	178	2	221]
136	LEFT ARROW	179	3	222	^
137	CTRL I	180	4	223	
138	LINE FEED	181	5	224	SPACE
139	CTRL K	182	6	225	a
140	CTRL L	183	7	226	b
141	CARR RTN	184	8	227	c
142	CTRL N	185	9	228	d
143	CTRL O	186	:	229	e
144	CTRL P	187	.	230	f
145	CTRL Q	188	<	231	g
146	CTRL R	189	=	232	h
147	CTRL S	190	>	233	i
148	CTRL T	191	?	234	j
149	RIGHT ARROW	192	@	235	k
150	CTRL V	193	A	236	l
151	CTRL W	194	B	237	m
152	CTRL X	195	C	238	n
153	CTRL Y	196	D	239	o
154	CTRL Z	197	E	240	p
155	ESC	198	F	241	q
156	FS	199	G	242	r
157	SHIFT CTRL-M	200	H	243	s
158	SHIFT CTRL-N	201	I	244	t
159	US	202	J	245	u
160	SPACE	203	K	246	v
161	!	204	L	247	w
162	"	205	M	248	x
163	#	206	N	249	y
164	\$	207	O	250	z
165	%	208	P	251	.
166	&	209	Q	252	<
167	'	210	R	253	=
168	(211	S	254	>
169)	212	T	255	
170	*	213	U		

The Original
Word
Processing
System

EasyWriter™

The Original System

Reference Card





**Information Unlimited
Software, Inc.**
281 Arlington Ave.
Berkeley, CA 94707
415-525-9452



How to get CONTROL

Here is the diamond
for cursor control.
Just hold the CTRL key.



CONTROL — W: Moves the cursor **up**
 CONTROL — S: Moves the cursor **to** the right
 CONTROL — Z: Moves the cursor **down**
 CONTROL — A: Moves the cursor **to** the left
 CONTROL — Q: Toggles cursor to **top** left/bottom left
 CONTROL — X: Scrolls text up one **screen**
 CONTROL — E: Scrolls text down **one** screen
 CONTROL — R: Scrolls text to **begin**ing of file
 CONTROL — T: TAB 8 spaces (**Exp**ress Tab)
 CONTROL — D: Deletes single **char**acter
 CONTROL — Y: Deletes entire line
 CONTROL — G: Line insert mode (**Togg**les On & Off)
 CONTROL — F: Character insert **mode**

Printer Formatting Commands

All formatting commands must be **pre**ceeded by two (SHIFT-M) characters. The lower case (n) represents a number in the following functions:
 (i e .M5 sets the margin to 5 spaces)


.N0 Disables page numbering
 .Nn Start numbering with **page** n
 .P1 Page pause on
 .P0 Page pause off
 .C Centers text
 .Mn Left margin
 .In Paragraph indentation
 .Sn Line spacing
 .Ln Line length
 .J0 Justification on
 .J1 Justification off
 .Gn Page length
 .F0 Form feed off
 .F1 Form feed on
 .Un User definable **char**acter
 .E Stop printing
 .B Restarts printing
 .H1 Early page eject (with **form** feed on)
 .An Page spacing (with **form** feed off)
 .D0 Disables incremental **spacing**
 .Dn Enables incremental **spacing***
 .T Clear Tabs
 .Tsn TAB symbol and amount

*Incremental Spacing

This command is (.Dn), where n = HMI (Horizontal Motion Index). Usually in the 11-14 range, will right-justify an 8½ x 11 page **perfectly**.

NOTE: This command only works with the Qume, Diablo, or Spinwriter printers.

Sample Set Up



EasyMailer Formatting Commands

.Y1 End of document eject on
 .Y0 End of document eject off
 .Zs Set fetch symbol s = symbol

